

Bay Trail CapsuleGen Tool User Guide

User Guide

March 2013

Revision 0.5

Intel Confidential



INFORMATION IN THIS DOCUMENT IS PROVIDED IN CONNECTION WITH INTEL PRODUCTS. NO LICENSE, EXPRESS OR IMPLIED, BY ESTOPPEL OR OTHERWISE, TO ANY INTELLECTUAL PROPERTY RIGHTS IS GRANTED BY THIS DOCUMENT. EXCEPT AS PROVIDED IN INTEL'S TERMS AND CONDITIONS OF SALE FOR SUCH PRODUCTS, INTEL ASSUMES NO LIABILITY WHATSOEVER AND INTEL DISCLAIMS ANY EXPRESS OR IMPLIED WARRANTY, RELATING TO SALE AND/OR USE OF INTEL PRODUCTS INCLUDING LIABILITY OR WARRANTIES RELATING TO FITNESS FOR A PARTICULAR PURPOSE, MERCHANTABILITY, OR INFRINGEMENT OF ANY PATENT, COPYRIGHT OR OTHER INTELLECTUAL PROPERTY RIGHT.

A "Mission Critical Application" is any application in which failure of the Intel Product could result, directly or indirectly, in personal injury or death. SHOULD YOU PURCHASE OR USE INTEL'S PRODUCTS FOR ANY SUCH MISSION CRITICAL APPLICATION, YOU SHALL INDEMNIFY AND HOLD INTEL AND ITS SUBSIDIARIES, SUBCONTRACTORS AND AFFILIATES, AND THE DIRECTORS, OFFICERS, AND EMPLOYEES OF EACH, HARMLESS AGAINST ALL CLAIMS COSTS, DAMAGES, AND EXPENSES AND REASONABLE ATTORNEYS' FEES ARISING OUT OF, DIRECTLY OR INDIRECTLY, ANY CLAIM OF PRODUCT LIABILITY, PERSONAL INJURY, OR DEATH ARISING IN ANY WAY OUT OF SUCH MISSION CRITICAL APPLICATION, WHETHER OR NOT INTEL OR ITS SUBCONTRACTOR WAS NEGLIGENT IN THE DESIGN, MANUFACTURE, OR WARNING OF THE INTEL PRODUCT OR ANY OF ITS PARTS.

Intel may make changes to specifications and product descriptions at any time, without notice. Designers must not rely on the absence or characteristics of any features or instructions marked "reserved" or "undefined". Intel reserves these for future definition and shall have no responsibility whatsoever for conflicts or incompatibilities arising from future changes to them. The information here is subject to change without notice. Do not finalize a design with this information.

The products described in this document may contain design defects or errors known as errata which may cause the product to deviate from published specifications. Current characterized errata are available on request.

Contact your local Intel sales office or your distributor to obtain the latest specifications and before placing your product order.

Copies of documents which have an order number and are referenced in this document, or other Intel literature, may be obtained by calling 1-800-548-4725, or go to: <http://www.intel.com/design/literature.htm%20>

This document contains information on products in the design phase of development.


All products, platforms, dates, and figures specified are preliminary based on current expectations, and are subject to change without notice. All dates specified are target dates, are provided for planning purposes only and are subject to change.

Code names featured are used internally within Intel to identify products that are in development and not yet publicly announced for release. Customers, licensees and other third parties are not authorized by Intel to use code names in advertising, promotion or marketing of any product or services and any such use of Intel's internal code names is at the sole risk of the user.

Intel and the Intel logo are trademarks of Intel Corporation in the U.S. and other countries.

*Other names and brands may be claimed as the property of others.

Copyright © 2013, Intel Corporation. All rights reserved.



Contents

1	Bay Trail CapsuleGen Tool User Guide	5
1.1	Installation.....	5
1.2	Run the Tool	5
1.2.1	Command Mode	5
1.2.1.1	Mandatory Command Options.....	5
1.2.1.2	Optional Command Options.....	6
1.2.2	UI Mode	6
1.3	Failure case.....	6



Revision History

Date	Revision	Description
March 2013	0.5	Initial release.

§



1 Bay Trail CapsuleGen Tool User Guide

The GenCapsule.exe tool is provided to create Capsule Firmware Volume by combining firmware update DXE with the firmware image to be updated. It also adds version information into the Capsule Firmware Volume consumed later by UpdateCapsule BIOS service.

The output of this tool is BIOSUpdate.fv. This output is later used by DFUDriverGen tool to generate the firmware update Windows* driver package. You can rename the output to follow your own naming convention before feeding the output to DFUDriverGen tool.

1.1 Installation

Installation of GenCapsule tool is straightforward. Copy the GenCapsule directory to the machine that this tool is to be run.

1.2 Run the Tool

The tool supports to be run in command mode only.

1.2.1 Command Mode

The tool runs in command mode if you specify any options as mentioned below:

1.2.1.1 Mandatory Command Options

-dx <Path to DXE driver binary>

This option is mandatory. The dx driver should already be UEFI signed for secure boot. This DXE driver is the update logic in the Capsule FV.

-cur <current version number>

This option is mandatory. The valid version number should be an unsigned 32-bit integer value. It specifies the version of firmware binary to be updated.

-min <minimum compatible firmware version number>

This option is mandatory. The valid minimum compatible firmware version number should be an unsigned 32-bit integer value. It specifies, after this new firmware is updated, what the lowest firmware version is that the system allows rolling back to. Normally this should be set equal to "cur" version number to avoid rollback of firmware.



-b <path of firmware binary file>

This option is mandatory. It specifies the firmware binary to be updated by the DXE in the Capsule FV.

1.2.1.1.1 Sample usage:

```
>GenCapsule.exe -cur 4 -min 4 -dxs FirmwareUpdate.efi -b firmwareImage.bin
```

1.2.1.2 Optional Command Options

-h

Optional and cannot combine with other options. This option provides tool help. Will provide prompt of usage when specified as the only option to the application.

1.2.1.2.1 Sample usage:

```
>GenCapsule.exe -h
```

1.2.1.2.2 Sample output:

The output of the tool is BIOSUPADATE.fv. You can rename it according to your firmware update naming convention.

1.2.2 UI Mode

This tool does not support to be run in UI mode.

1.3 Failure case

This tool does not support to be run in UI mode.